

STEP-BY-STEP INSTRUCTIONS I

INDESIGN: PRINT SETTINGS FOR PANTONE PLUS COLOURS

InDesign print settings for your Epson photo printer

Before you start, ensure you are using the best and most up-to-date version of everything (firmware, printer drivers etc.) and calibrate your printer. Create your file with PANTONE PLUS colours.

Please follow the steps below and select the highlighted print settings for the best possible print results (You can leave all other settings unchanged or select individual ones as required):

Color Settings

Unsyncronized: Your Creative Suite applications are not synchronized for consistent color. To synchronize, select Suite Color Settings in Bridge.

Settings: Custom
☒ Advanced Mode

1 Working Spaces

RGB: Adobe RGB (1998)
CMYK: ISO Coated v2 (ECI)

Color Management Policies

RGB: Off
CMYK: Off

Profile Mismatches: ☐ Ask When Opening
☐ Ask When Pasting

Missing Profiles: ☐ Ask When Opening

2 Conversion Options

Engine: Adobe (ACE)
Intent: Absolute Colorimetric
☒ Use Black Point Compensation

Description:
Position the pointer over a heading to view a description.

New Color Swatch

Swatch Name: PANTONE 100 C

☐ Name with Color Value

3 Color Type: Spot
Color Mode: RGB

Red: 241
Green: 227
Blue: 101

☐ Preview

Print

Print Preset: [Custom]
4 Printer: Your Epson photo printer
PPD: [Printer + Premium Semimatte Photo Paper (260)]

Color Management

Print:
☐ Document (Profile: Adobe RGB (1998))
☒ Proof (Profile: ISO Coated v2 (ECI))

5 Options

Color Handling: Let InDesign Determine Colours
Printer Profile: Printer + Premium Semimatte Photo Paper (260)
Output Color: Composite RGB
☐ Preserve RGB Numbers
☐ Simulate Paper Color

Description:
Position the pointer over a heading to view a description.

Save Preset... Page Setup... Print Cancel

Current Settings

Main
Media Type: Premium Semimatte Photo Paper (260)
6 Print Quality Level: LEVEL 5
Print Quality: SuperPhoto - 2880x1440dpi
High Speed: Off

Color:
Source: Roll Paper
Auto Cut: Normal Cut
Auto Rotate: Off

Page Layout
Orientation: Portrait
Rotate 180°: Off
Copies: 1
Size: Pantone

Job Settings: Off

Color Correction
Color Adjustment: Off (No Color Adjustment)

☒ Always show Current Settings.

Properties of your Epson photo printer

Main Page Layout Utility

Select Setting: Current Settings Save/Del...

6 Media Settings

Media Type: Premium Semimatte Photo Paper (260)
Color: Color
Print Quality: Quality Options
Mode: ☒ Automatic ☒ Custom
8 Off (No Color Adjustment)

Paper Settings
Source: Roll Paper
Size: Pantone
☐ Borderless

☐ Print Preview
☐ Layout Manager

Ink Levels
GR LLK Y LC VLM OR MK VM LK C PK

Reset Defaults(Y) Version 6.73

OK Cancel Help

Any questions? If so, please contact your dealer for further information.

STEP-BY-STEP INSTRUCTIONS I

INDESIGN: PRINT SETTINGS FOR PANTONE PLUS COLOURS

InDesign print settings for your Canon photo printer

Before you start, ensure you are using the best and most up-to-date version of everything (firmware, printer drivers etc.) and, if possible, calibrate your printer to PANTONE® VIBRANT by Felix Schoeller. Create your file with PANTONE PLUS colours. Please follow the steps below and select the highlighted print settings for the best possible print results (You can leave all other settings unchanged or select individual ones as required):

Color Settings

Unsyncronized: Your Creative Suite applications are not synchronized for consistent color. To synchronize, select Suite Color Settings in Bridge.

Settings: Custom
☒ Advanced Mode

Working Spaces

1 RGB: Adobe RGB (1998)
CMYK: ISO Coated v2 (ECI)

Color Management Policies

RGB: Off
CMYK: Off

Profile Mismatches: ☐ Ask When Opening
☐ Ask When Pasting

Missing Profiles: ☐ Ask When Opening

Conversion Options

2 Engine: Adobe (ACE)
Intent: Absolute Colorimetric
☒ Use Black Point Compensation

Description:
Position the pointer over a heading to view a description.

New Color Swatch

Swatch Name: PANTONE 100 C
☐ Name with Color Value

3 Color Type: Spot
Color Mode: RGB

Red: 241
Green: 227
Blue: 101

☐ Preview

Print

Print Preset: [Custom]
4 Printer: Your Canon photo printer
PPD: [None]

Color Management

Print:
☐ Document (Profile: Adobe RGB (1998))
☒ Proof (Profile: ISO Coated v2 (ECI))

Options:
5 Color Handling: Let InDesign Determine Colours
Printer Profile: Printer + Semi-Glossy Photo Paper HG 255

Output Color: Composite RGB
☐ Preserve RGB Numbers
☐ Simulate Paper Color

Description:
Position the pointer over a heading to view a description.

Save Preset... Page Setup... Print Cancel

Properties of your Canon photo printer

Main Page Setup Layout Favorites Utility Support

6 Media Type: Semi-Glossy Photo Paper HG 255

Get Information... Advanced Settings...

Advanced Settings

Print Priority: Image

7 Print Quality: Highest (600dpi)

8 Color Mode: No color correction

Color Settings...

☐ Thicken Fine Lines
☐ Unidirectional Printing

☐ Open Preview When Print Job Starts

Status Monitor... About Defaults

OK Cancel Help

Any questions? If so, please contact your dealer for further information.